

Domoticz

Explore Custom Pages


Highcharts & Google Charts

Developed For Personal Use


22.11.2020

Selected Examples


Highcharts Line Chart




Highcharts Angular Gauges



Highcharts Combined Chart




Google Charts Gauges



INFO: More examples in the archive *"explore_custom_pages_charts.zip"*.

Multiple Devices Chart Concept








Two Data Source Solutions:

1. Domoticz Text Device
2. External Data File

Test Scenario

Test Scenario Devices

Idx	Hardware	ID	Unit	Name	Type	SubType	Data
 30	VirtualSensors	001406E	1	MakeLab Thermostat Setpoint	Thermostat	SetPoint	21.5
 31	VirtualSensors	1406F	1	MakeLab Temperature	Temp	LaCrosse TX3	24.5 C
 32	VirtualSensors	00082032	1	MakeLab Thermostat Battery	General	Percentage	30%
 42	VirtualSensors	00082042	1	MakeLab Thermostat Data	General	Text	1025;21.5;20.5
 43	VirtualSensors	00082043	1	MakeLab Thermostat JSON	General	Text	{"timestamp":"1235", "devices": [{"name":"MakeLab Thermostat Setpoint", "data":17.5}, {"name":"MakeLab Temperature", "data":19.5}]}

Test Scenario Value Flow with dzVents device attributes


IDX 30 setPoint + IDX 31 temperature = IDX 42 HHMM;setPoint;temperature

IDX 30 Name & setPoint + IDX 31 Name & temperature = IDX 43 JSON Object
{
 "timestamp": "HHMM",
 "devices": [
 {"name":"name", "data":setPoint}, {"name":"name", "data":temperature}
]
}

IDX 30 setPoint + IDX 31 temperature = External File JSON Object
{
 "result" : [
 {"pv":setPoint,"sp":temperature,"time":"12:38"},
 ...
],
 "status":"OK",
 "title":"Thermostat Data"
}

Highcharts


Set Point (SP) & Temperature (PV) 24 hour data (sample rate 5 mins)



```
Data Content HTTP API Response
{
  "result" : [
    {
      "Data" : "0913;18.5;21.5",
      "Date" : "2020-11-05 09:13:00",
      "User" : "",
      "idx" : "4"
    },
    ... ],
  "status" : "OK",
  "title" : "TextLog"
}
```

Item	Description
File Source	highcharts\linechart\datatextcsv\thermostat-1dayview.html (archive: explore_custom_pages_charts.zip)
Data Source	Domoticz virtual sensor Text Device History Log with 1 day setting (datatextcsv)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=textlog&idx=IDX</i> Text Device
Data Content	CSV string: HHMM;SP;PV from the HTTP API Response key Data
Chart Additions	xAxis labels first & last only; Credit information disabled

Set Point (SP) & Temperature (PV) 24 hour data (sample rate 5 mins) with chart additions.




Data Content HTTP API Response

```
{
  "result" : [
    {
      "Data" : "0913;18.5;21.5",
      "Date" : "2020-11-05 09:13:00",
      "User" : "",
      "idx" : "4"
    },
    ... ],
  "status" : "OK",
  "title" : "TextLog"
}
```

Item	Description
File Source	highcharts\linechart\datatextcsv\thermostat-1dayview-advanced.html (archive: explore_custom_pages_charts.zip)
Data Source	Domoticz virtual sensor Text Device History Log with 1 day setting (datatextcsv)
Data Source Location	Domoticz HTTP API Request: http://domoticz-ip:port/json.htm?type=textlog&idx=IDX Text Device
Data Content	CSV string: HHMM;SP;PV from the HTTP API Response key Data
Chart Additions	<ul style="list-style-type: none">Data series as array with device name, datapoints, line colorChart series legend with Min, Max, AvgPlot line at midnightChart credits with last update and link to view the log of the text device with datapointsCustomized context menu with own function Refresh, two standard menu items (Download ...) and About Dialog (Bootbox)


Set Point (SP) & Temperature (PV) (sample rate 5 mins)



```
Data Content File with JSON Object
{
  "result" : [
    {"pv":16.5,"sp":17.5,"time":"12:38"},
    ...
  ],
  "status":"OK",
  "title":"Thermostat Data"
}
```

Item	Description
File Source	highcharts\linechart\datafilejson\thermostat-1dayview.html (archive: explore_custom_pages_charts.zip)
Data Source	External file with JSON object created in regular intervals by dzVents using persistent data (datafilejson)
Data Source Location	~domoticz/www/templates/thermostat_1dayview_data.json
Data Content	JSON array "result" with key:value pairs = "pv": NN.N, "sp": NN.N, "time": HH:MM
Chart Additions	xAxis title with PV Min, Max, Avg

Four Temperature Devices selected from Domoticz Room Plan




Data Content HTTP API Response

```
{
  "ServerTime" : "2020-11-09 19:28:40",
  "result" :
  [
    {"Name" : "Aussen",
      "Temp" : 7.7,
      "idx" : "344"},
    {"Name" : "Wohnen",
      "Temp" : 21,
      "idx" : "350"},
    {"Name" : "Server Raum",
      "Temp" : 16.1,
      "idx" : "351"},
    {"Name" : "Keller Gro\u00dfraum",
      "Temp" : 18.5,
      "idx" : "356"},
  ],
  "status" : "OK",
  "title" : "Devices"
}
```

Item	Description
File Source	highcharts\angulargaugeschart\datahttpplan\temperature-dashboard.html (archive: explore_custom_pages_charts.zip)
Data Source	Temperature Devices data (datahttpplan)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=devices&plan=IDX ROOMPLAN</i>
Data Content	JSON array “result” with key:value pairs
Chart Additions	4 Gauges as individual Highcharts Angular Gauges charts added to HTML DIV container as child


Four Devices selected from Domoticz Room Plan



```
Data Content HTTP API Response
{
  "ServerTime" : "2020-11-09 19:28:40",
  "result" :
  [
    {"Name" : "Aussen",
     "Temp" : 7.7,
     "idx" : "344"},
    {"Name" : "Wohnen",
     "Temp" : 21,
     "idx" : "350"},
    {"Name" : "Server Raum",
     "Temp" : 16.1,
     "idx" : "351"},
    {"Name" : "Keller Gro\u00dfraum",
     "Temp" : 18.5,
     "idx" : "356"},
  ],
  "status" : "OK",
  "title" : "Devices"
}
```

Item	Description
File Source	highcharts\columnchart\datahttpplan\temperature-dashboard.html (archive: explore_custom_pages_charts.zip)
Data Source	Temperature Devices data (datahttpplan)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=devices&plan=IDX ROOMPLAN</i>
Data Content	JSON array "result" with key:value pairs
Chart Additions	Custom menu; Footer as HTML table outside chart area


Set Point (SP), Temperature (PV), Deviation (Dev)



```
Data Content HTTP API Response
{
  "app_version" : "2020.2 (build 12554)",
  "result" : [
    {
      ...
      "Data" : "0913;21.0;24.0",
      "Name" : "MakeLab Thermostat Data",
      ...
      "idx" : "42"
    }
  ],
  "status" : "OK",
  "title" : "Devices"
}
```

Item	Description
File Source	highcharts\angulargaugeschart\datahttprid\thermostat-dashboard-vu.html (archive: explore_custom_pages_charts.zip)
Data Source	Temperature Devices data (datahttprid)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=devices&rid=IDX THERMOSTAT</i>
Data Content	CSV string: HHMM;SP;PV from the HTTP API Response key result[0].Data
Chart Additions	Footer with refresh button, Last Update & Version information

Set Point (SP), Temperature (PV) & Deviation (Dev) 24 hour data (sample rate 5 mins)




```
Data Content HTTP API Response
{
  "result" : [
    {
      "Data" : "0913;19.5;21.5",
      "Date" : "2020-11-05 09:13:00",
      "User" : "",
      "idx" : "4"
    },
    ... ],
  "status" : "OK",
  "title" : "TextLog"
}
```

Item	Description
File Source	highcharts\columnlinechart\datatextcsv\thermostat-1dayview.html (archive: explore_custom_pages_charts.zip)
Data Source	Domoticz virtual sensor Text Device History Log with 1 day setting (datatextcsv)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=textlog&idx=IDX</i> Text Device
Data Content	CSV string: HHMM;SP;PV from the HTTP API Response key result[NNN].Data
Chart Additions	Credits bottom centre Last Update + Version; xAxis plot lines to built box around column chart; xAxis label last value only

Google Charts

Set Point (SP) & Temperature (PV) 24 hour data (sample rate 5 mins)




Data Content HTTP API Response

```
{
  "result" : [
    {
      "Data" : "0913;19.5;21.5",
      "Date" : "2020-11-05 09:13:00",
      "User" : "",
      "idx" : "4"
    },
    ... ],
  "status" : "OK",
  "title" : "TextLog"
}
```

Item	Description
File Source	googlecharts\linechart\datatextcsv\thermostat-1dayview.html (archive: explore_custom_pages_charts.zip)
Data Source	Domoticz virtual sensor Text Device History Log with 1 day setting (datatextcsv)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=textlog&idx=IDX</i> Text Device
Data Content	CSV string: HHMM;SP;PV from the HTTP API Response key Data
Chart Additions	Table footer with refresh button, update & PV min/max/avg and version information


Set Point (SP), Temperature (PV) & Deviation (Dev)



```
Data Content HTTP API Response
{
  "app_version" : "2020.2 (build 12554)",
  "result" : [
    { ...
      "Data" : "0913;21.0;24.0",
      "Name" : "MakeLab Thermostat Data",
      ...,
      "idx" : "42"
    }
  ],
  "status" : "OK",
  "title" : "Devices"
}
```

Item	Description
File Source	googlecharts\gaugeschart\datahttprid\thermostat_dashboard.html (archive: explore_custom_pages_charts.zip)
Data Source	Domoticz virtual sensor Text Device Status (datahttprid)
Data Source Location	Domoticz HTTP API Request: <i>http://domoticz-ip:port/json.htm?type=devices&rid=IDX</i> Text Device
Data Content	CSV string: HHMM;SP;PV from the HTTP API Response key Data
Chart Additions	Chart device name; Table footer with refresh button, update & PV min/max/avg and version information

Set Point (SP), Temperature (PV) & Deviation (Dev) & line chart 24 hours data (sample rate 5 mins)



```
Data Content JSON File
{
  "result" : [
    {"pv":22.0,"sp":22.0,"time":"11:17"},
    {"pv":25.0,"sp":22.0,"time":"11:16"},
    ...],
    "status":"OK",
    "title":"Thermostat Data"
  }
}
```

Item	Description
File Source	googlecharts\gaugeslinechart\datajsonfile\thermostat_1dayview.html (archive: explore_custom_pages_charts.zip)
Data Source	External file with JSON object created in regular intervals by dzVents using persistent data (datajsonfile)
Data Source Location	~domoticz/www/templates/thermostat_1dayview_data.json
Data Content	JSON array “result” with JSON data in key result.Data
Chart Additions	Table with row gauges; row refresh button + info; row table 1 day view

Automation Scripts dzVents

```
On Off thermostat_data_textcsv

-- Idx of the devices
local IDX_SP = 30 -- Thermostat Temperature SetPoint (SP); Device: Thermostat, SetPoint
local IDX_PV = 31 -- Thermostat Temperature Process Value (PV); Device: Temp, LaCrosse TX3
local IDX_TS = 42 -- Text device holding the data as CSV string; Device: General, Text

return
{
  on =
  {
    timer =
    {
      'every 5 minutes at 00:00-23:59',
      -- 'every minute',
    },
  },
  logging =
  {
    level = domoticz.LOG_INFO,
    marker = 'THERMOSTATDATATEXTCSV',
  },
  execute = function(domoticz)
    -- Store the new data in the virtual text sensor as CSV string (max length 200)
    -- Content is: hhmm,sp,pv
    local data = ("%s%s;%.1f;%.1f"):format(
      string.format("%02d", domoticz.time.hour),
      string.format("%02d", domoticz.time.minutes),
      domoticz.utils.round(domoticz.devices(IDX_SP).setPoint, 1),
      domoticz.utils.round(domoticz.devices(IDX_PV).temperature, 1)
    )
    -- Log the value & update text device
    domoticz.log(data)
    domoticz.devices(IDX_TS).updateText(data);
  end
}

On Off thermostat_data_textjson

-- Idx of the devices
local IDX_SP = 30 -- Thermostat Temperature SetPoint (SP); Device: Thermostat, SetPoint
local IDX_PV = 31 -- Thermostat Temperature Process Value (PV); Device: Temp, LaCrosse TX3
local IDX_JSON = 43 -- Text device holding the data JSON string; Device: General, Text

return
{
  on =
  {
    timer =
    {
      'every 5 minutes at 00:00-23:59',
      -- 'every minute',
    },
  },
  logging =
  {
    level = domoticz.LOG_INFO,
    marker = 'THERMOSTATDATATEXJSON',
  },
  execute = function(domoticz)
    -- Store the new data in the virtual text sensor as JSON object (max length 200)
    local jsonData = (
      '{"timestamp": "%s", "devices": [{"name": "%s", "data": %.1f}, {"name": "%s", "data": %.1f}]}':format(
        string.format("%02d", domoticz.time.hour),
        string.format("%02d", domoticz.time.minutes),
        domoticz.devices(IDX_SP).name,
        domoticz.utils.round(domoticz.devices(IDX_SP).setPoint, 1),
        domoticz.devices(IDX_PV).name,
        domoticz.utils.round(domoticz.devices(IDX_PV).temperature, 1)
      )
    )
    -- Log and Update
    domoticz.log(jsonData)
    domoticz.devices(IDX_JSON).updateText(jsonData)
  end
}
```

2020-11-22 09:35:10 🌞▲08:01 ▼16:14 Room: All

Temperature Sensors

MakeLab Temperature 22.5° C

Utility Sensors

MakeLab Thermostat Setpoint 19.5° C

MakeLab Thermostat Data 0935;19.5;21.5

MakeLab Thermostat JSON {"timestamp": "1845", "devices": [{"name": "MakeLab Thermostat Setpoint", "data": 19.5}, {"name": "MakeLab Temperature", "data": 21.5}]}

dzVents - CSV String

Example Text Device Value CSV String HHMM;Value1;ValueN
0913;18.5;21.5

Example snippet dzVents timer trigger to create the CSV string & update the text device

```
local IDX_SP = 30    -- Thermostat Temperature SetPoint (SP); Device: Thermostat, SetPoint
local IDX_PV = 31    -- Thermostat Temperature Process Value (PV); Device: Temp, LaCrosse TX3
local IDX_TS = 42    -- Text device holding the data as CSV string; Device: General, Text

return
{
  on = {
    timer = {
      'every 5 minutes at 00:00-23:59'
    },
  },
  logging = {
    level = domoticz.LOG_INFO, marker = 'THERMOSTATDATA',
  },
  execute = function(domoticz)
    -- Store the new data in the virtual text sensor as CSV string (max length 200): hhmm,sp,pv
    domoticz.devices(IDX_TS).updateText(("%%s%%s;%.1f;%.1f"):format(
      string.format("%02d", domoticz.time.hour),
      string.format("%02d", domoticz.time.minutes),
      domoticz.utils.round(domoticz.devices(IDX_SP).setPoint, 1),
      domoticz.utils.round(domoticz.devices(IDX_PV).temperature, 1)
    ));
    -- Log the value
    domoticz.log(domoticz.devices(IDX_TS).text)
  end
}
```

Date	
2020-11-22 09:10:00	0910;19.5;22.5
2020-11-22 09:05:00	0905;19.5;18.5
2020-11-22 09:00:00	0900;19.5;18.5

dzVents - JSON Object

Example Text Device JSON Object - each datapoint has a JSON object with in this case 2 devices

```
{
  "result" :
    [{"Data":"SEE BELOW","Date":"2020-11-13 18:00:00","User":"","idx":"1999"}, ... ],
  "status":"OK","title":"TextLog"
}
```

The Data key is a JSON string:

```
"Data" : "{
  "timestamp":"1800","devices":[
    {"name":"MakeLab Thermostat Setpoint", "data":17.5},
    {"name":"MakeLab Temperature", "data":16.5}]
}"
```

Example snippet dzVents timer trigger to create the JSON object & update the text device

```
local IDX_SP = 30    -- Thermostat Temperature SetPoint (SP); Device: Thermostat, SetPoint
local IDX_PV = 31    -- Thermostat Temperature Process Value (PV); Device: Temp, LaCrosse TX3
local IDX_JSON = 43  -- Text device holding the data JSON string; Device: General, Text
```

```
local jsonData = (
  '{"timestamp":"%s%s", "devices":[{"name":"%s", "data":%.1f}, {"name":"%s", "data":%.1f}]}' :format(
    string.format("%02d", domoticz.time.hour),
    string.format("%02d", domoticz.time.minutes),
    domoticz.devices(IDX_SP).name,
    domoticz.utils.round(domoticz.devices(IDX_SP).setPoint, 1),
    domoticz.devices(IDX_PV).name,
    domoticz.utils.round(domoticz.devices(IDX_PV).temperature, 1)
  )
)
domoticz.devices(IDX_JSON).updateText(("s"):format(jsonData))
```

Date	Data
2020-11-21 18:45:00	{"timestamp":"1845", "devices":[{"name":"MakeLab Thermostat Setpoint", "data":19.5}, {"name":"MakeLab Temperature", "data":21.5}]}
2020-11-21 18:40:00	{"timestamp":"1840", "devices":[{"name":"MakeLab Thermostat Setpoint", "data":19.5}, {"name":"MakeLab Temperature", "data":22.5}]}
2020-11-21 18:35:00	{"timestamp":"1835", "devices":[{"name":"MakeLab Thermostat Setpoint", "data":19.5}, {"name":"MakeLab Temperature", "data":22.5}]}